



Spanning tree Tuning

Pietro Nicoletti
www.studioreti.it



Copyright note

- These slides are protected by copyright and international treaties. The title and the copyrights concerning the slides (inclusive, but not only, every image, photograph, animation, video, audio, music and text) are the author's (see Page 1) property.
- The slides can be copied and used by research institutes, schools and universities affiliated to the Ministry of Public Instruction and the Ministry of University and Scientific Research and Technology, for institutional purpose, not for profit. In this case there is not requested any authorization.
- Any other complete or partial use or reproduction (inclusive, but not only, reproduction on discs, networks and printers) is forbidden without written authorization of the author in advance.
- The information contained in these slides are believed correct at the moment of publication. They are supplied only for didactic purpose and not to be used for installation-projects, products, networks etc. However, there might be changes without notice. The authors are not responsible for the content of the slides.
- In any case there can not be declared conformity with the information contained in these slides.
- In any case this note of copyright may never be removed and must be written also in case of partial use.



Timers for Maximum Bridge Diameter 2 ÷ 13 & default hello time

- Maintaining default hello time (2 s)

Max bridge diameter	2	3	4	5	6	7	8	9	10	11	12	13
Hello Time	2	2	2	2	2	2	2	2	2	2	2	2
Max age	10	12	14	16	18	20	22	24	26	28	30	32
Forward delay	7	9	10	12	13	15	16	18	19	21	22	24
Reconfig. time	24	30	34	40	44	50	54	60	64	70	74	80



Timers for Maximum Bridge Diameter 2 ÷ 13 & minimum hello time

- Setting hello time to the value of 1 s

Max bridge diameter	2	3	4	5	6	7	8	9	10	11	12	13
Hello Time	1	1	1	1	1	1	1	1	1	1	1	1
Max age	6	7	9	10	12	13	14	16	18	19	21	22
Forward delay	4	5	6	7	8	9	10	11	12	13	14	15
Reconfig. time	14	17	21	24	28	31	34	38	42	45	49	52



Timers for Maximum Bridge Diameter 14 ÷ 25 & minimum hello time

- Setting hello time to the value of 1 s

Max bridge diameter	14	15	16	17	18	19	20	21	22	23	24	25
Hello Time	1	1	1	1	1	1	1	1	1	1	1	1
Max age	24	25	27	28	30	31	33	34	36	37	39	40
Forward delay	16	17	18	19	20	21	22	23	24	25	26	27
Reconfig. time	56	59	63	66	70	73	77	80	84	87	91	94